


## LabVIEW Evaluation Series: Acquire and Analyze Signals with LabVIEW Real-Time

Learn how to add a real-time target to your project and then create an application to deterministically acquire data and analyze it with ready-to-run libraries built into LabVIEW.


### Starting a New Project in LabVIEW and Adding a Real-Time Target

Begin by creating a new project in LabVIEW, where you will manage your code and hardware resources.


1. Create a new project in LabVIEW by selecting **File » Create Project**. Then select **Blank Project**.




2. In the default project tree you have **My Computer**, which is where you can write code that will run on the Windows machine you're currently developing on. Remember that a Real-Time target has a processor running a real-time operating system, so effectively, it's another computer. To write code that will run on that computer, you need to add another target to your project. To add a real-time system to the project, right-click on the Project item at the top of the tree and select **New » Targets and Devices...**




3. This dialog allows you to discover existing systems on your network or add a new system. Since you are just evaluating the software, select **New target or device**. LabVIEW lists available hardware corresponding with the drivers you have installed. Since you installed the NI-RIO driver with your evaluation software, select and expand **Real-Time CompactRIO**, then select **cRIO-9068**.




4. If you had an existing system, LabVIEW would now attempt to detect the I/O present in your system and automatically add them to the LabVIEW Project. Since we are adding a new system, we'll need to manually add a C Series I/O module. To do this, right-click on the Chassis project item, named for the backplane of a CompactRIO, and select **New » C Series Modules...**




5. In the same manner as the target, since you do not have physical hardware, select **New target or device**, select **C Series Module**, then click **OK**.



6. In the dialog box that appears, select an NI 9211 Thermocouple module for Mod 1 then click **OK**.




7. You are now ready to start programming and accessing I/O on your real-time target. Navigate to **File » Save** to save your project as **Real-Time Evaluation.lvproj**. Click **OK**. Note that you would communicate to your target by entering its IP Address once it's properly configured on the same network as your development computer.




## Developing a LabVIEW Real-Time VI

This section will walk you through creating a basic real-time control application on [CompactRIO](#). You should now have a new LabVIEW Project that contains your CompactRIO system and C Series I/O module. In this tutorial we will be using an NI 9211 Thermocouple input module; however, the process can be followed for almost any analog input module.


1. This project will only contain one VI, which is the LabVIEW Real-Time application that runs embedded on the real-time processor. Create this the VI by right-clicking on the CompactRIO real-time controller in the project and selecting **New » VI**. Save the VI as *RT.vi*.




2. Double-click on **RT.vi** to open it. A VI is composed of two windows, the gray **Front Panel**, which serves as the user interface, and the white **Block Diagram**, where code is developed.
3. The basic operation of this application will include initialization and then two parallel tasks. A flat sequence structure is an easy way to enforce that initialization happens first in dataflow. In the white Block Diagram window, right-click in the blank space to bring up the Functions palette and then select **Programming » Structures » Flat Sequence Structure**.




- Now add a **Timed Loop** (right-click and select **Programming » Structures » Timed Structures » Timed Loop**) to the right of the sequence structure. Timed loops provide the ability to deterministically synchronize the code inside of them to various time bases, running continuously until a stop condition is met.




Drag with your mouse the rectangle where you want the loop to appear, then release.




- To configure the timed loop, double-click on the clock icon on the left input node.




6. Select **Synchronize to Scan Engine** as the Loop Timing Source. Click **OK**. This will cause the code in the timed loop to execute once, immediately after each I/O scan, ensuring that any I/O values used in this timed loop are the most recent values. The [NI Scan Engine](#) allows you to access I/O modules directly in LabVIEW Real-Time on a CompactRIO without programming LabVIEW FPGA.



7. The previous step configured the timed loop to run synchronized to the scan engine. Now configure the rate of the scan engine itself by right-clicking on the top-level *RT CompactRIO Target* in the LabVIEW Project and selecting **Properties**.




8. Select **Scan Engine** from the categories on the left and enter **100ms** as the *Scan Period*. This will cause all of the I/O in the CompactRIO system to be updated every 100ms (10Hz). The Network Publishing Period can also be set from this page, which controls how often the I/O values are published to the network for remote monitoring and debugging. Click **OK**.




9. Now that you have configured the I/O scan rate, it is time to add the I/O reads to your application for control. When using CompactRIO Scan Mode, you can simply drag and drop the I/O variables from the LabVIEW Project to the RT block diagram. Expand the CompactRIO chassis and I/O module. Select **AIO**,


click on it, then drag and drop it into the timed loop on your RT.vi diagram as shown below. Also drag **AI1** into the timed loop.



10. Next we will add analysis that runs on the target to the program. To do so right click the block diagram to open the Functions palette and click on the Search button in the top right of the palette.



11. Search for “Mean” and select **Mean PtByPt.vi** in the Signal Processing Palette and drag two instances to your block diagram in the timed loop and wire your I/O as shown in the image below. Create a constant by right-clicking on the **sample length** input terminal and type in a value of **100**.




12. The next logical step would be to write the data to the user interface; however, it’s a best practice to separate high priority acquisition from presenting or logging the data. This minimizes jitter and allows your timed loop to run with “real-time” performance, meaning that it will always finish on time. By running tasks in separate loops at distinct rates, you also maximize CPU efficiency by executing each task only as often as necessary.


You will transfer the latest result of the mean calculation from the high priority timed loop to a while loop using a real-time FIFO. This will provide a buffer between the two loops. The timed loop will run,




synchronized to the I/O scan, and write the latest result of the mean calculation to the buffer each time. The while loop will read the data out of the buffer and write it to the user interface to display temperature data at run time. Place down a **While Loop** beneath the timed loop (**Structures » While Loop**).




- Next, create the shared variables to transfer values between the high priority timed loop and low priority while loop. To create a shared variable right click your RT CompactRIO Target in the LabVIEW Project and select **New » Library**. Right-click on the new library and select **Save » Save**. Rename your library something intuitive like “RTComm” to be saved on disk and click **OK**.



- Now, right-click your new library and select **New » Variable**. This will open the Shared Variable Properties window. Name your variable **Data Buffer**, and select **Single Process** for the variable type in the Variable Type drop down box as shown in the image below. Choose **Array of Double** as the Data Type. This will create a locally scoped variable (no network publishing) that contains an array of double precision floating point numbers.




15. Select the **RT FIFO** option from the menu on the left and click the **Enable RT FIFO** check box. Then select **Single Element** for the FIFO Type, and enter **2** for the Number of elements (this would vary depending on the number of I/O channels monitored). This configures the variable to operate as global variable that can maintain the timing requirements, serving as a data buffer between the high priority and low priority tasks. Click **OK**.




16. Create another single process shared variable in the library you just created. This variable is for the Stop control we are going to create that will stop both loops of the program when directed. This new variable should have all the following settings:


- Name: **Stop**
- Variable Type: **Single Process**
- Data Type: **Boolean**
- RT FIFO: **Enabled** and **Single Element** FIFO Type




17. Once finished, your project should look similar to the image below.




18. Now return to the sequence structure to initialize these variables and an array for the data. Drag an instance of both variables from the project into the structure.




19. Right-click on each variable and select **Access Mode » Write**.




20. Right-click on each variable's input terminal and select **Create » Constant**. Leave the default False and array of zeros values.



21. Place an **Initialize Array.vi** in the structure (Search the Functions palette or navigate to **Programming » Array » Initialize Array**). Right-click the **element** terminal and **Create » Constant**. Set the value to **0**. Do the same for the **dimension size** input terminal and set the constant value to **2**, as you will write two channels of temperature data to the array. Then wire the **initialized array** output through the sequence structure to the border of the timed loop, as shown below.




22. Now insert the mean values into the array. Place two instances of the **Insert Into Array.vi** (**Programming » Array » Insert Into Array**) into the timed loop and wire the **mean** output into the **new element** terminal as shown below.




Place one **Insert Into Array.vi** after the other to build up the array, wiring the **output array** into the **array** input. The first **AI0** mean data point is placed into index **0** by default. Create a constant of **1** for the **index** input of the second **Insert Into Array.vi** to place the **AI1** mean data point into the next index.


23. Drag an instance of both the **Data Buffer** and **Stop** variables from the project into the timed loop. Wire the **output array** into the **Data Buffer** FIFO variable to transfer data to the while loop. Then wire the **Stop** variable to the **Loop Condition** terminal, as shown below.




24. Now we will create our user interface to see temperature data and stop the application at run time. Right-click on the Front Panel to bring up the Controls palette and select **Silver » Graph » Waveform Chart**. Then select **Silver » Boolean » Stop Button**. Arrange the user interface as shown below.



25. Now finish wiring the low priority while loop. Drag an instance of both the **Data Buffer** and **Stop** variables into the loop. Wire the **Data Buffer** output into the Waveform Chart, and the Stop Button control value into the **Stop** variable to ensure both loops stop at the same time. Also wire this stop value to the **Loop Condition**.



26. Place down a **Wait (ms).vi** to enforce timing for this task. Right-click on the input terminal and **Create » Constant**, entering a value of 200, to run slower than the high-priority while loop. Finally, Double-click on the **Waveform Chart** label to select it and rename it something meaningful, like **Temperature**.



27. Your basic acquisition and analysis application is now complete. Once you connect CompactRIO hardware you can run the code on the target.

## Additional Resources

[Do I Need a Real-Time System?](#)

[Using NI CompactRIO Scan Mode with NI LabVIEW Software](#)